

Go to <https://colab.research.google.com/>

1. Click **Upload notebook** and select `SADCP_STAprocc_colab_v3.ipynb`.
2. Wait for the notebook to open in Google Colab.
3. Start at the top of the notebook and work **from top to bottom**.
4. **Read the instructions above each cell before running it.** Some cells only need to be run, while others contain settings that you may need to change.
5. To **run a cell**, click the **play button** ► on the left side of the cell. You can also click inside the cell and press **Shift+Enter**. Wait for the cell to finish before continuing.
6. If a cell contains **user settings**, click directly in the code and edit the value. For example, change `transducer_depth = 6.0` to `transducer_depth = 5.0` if the transducer is 5 m below the sea surface. Then run the cell.
7. For settings with a choice, change **only the value inside the quotation marks**. For example, change `instrument = "WH600"` to `instrument = "OS150"` when using OS150 data.
8. For **True/False settings**, change only `True` to `False`, or vice versa. Do not add quotation marks.
9. Lines beginning with `#` are comments or alternative settings and are not executed. To switch between alternatives, move the `#` from the setting you want to use to the one you do not want to use.
10. When the notebook asks you to **upload an STA file**, run that cell and use the file-selection window that appears to select your `.STA` file.
11. Continue reading the instructions and running each cell **in order until you reach the end of the notebook**. Avoid skipping cells unless the instructions say that the cell is optional.
12. If you change a setting after later cells have already been run, run the changed cell again and then **rerun all cells below it**. An easy way to start over is **Runtime → Run all** (*Körning → Kör alla*).
13. At the end, run the **download-results cell** to save the generated results to your computer.

Tip: If something goes wrong, return to the top, check the settings, and run the notebook again from top to bottom.